



How to Save a Print-Ready PDF File from InDesign

1. under File - Adobe PDF Presets, use the existing preset "Press Quality". Change the Compatibility to "Acrobat 8/9 (PDF 1.7)".

Then make sure you are saving all the Pages as "Pages" and not "Spreads". Then View as "Fit Page" and Layout as "Single Page".



2. in the Compression tab, we need to set the pixels per inch to "350" for Color Images and "350" for Grayscale Images. Change the Compression type to "ZIP" in all three.

	Export Adobe PDF	1000
Adobe PDF Preset:	[Press Quality] (modified)	
Standaru:	None + Compatibility: Acrobat 8/9 (PDF 1.7)	
	Compression	
Compression	Color Images	
Marks and Eleeds	Bicubic Downsampling to	
Advanced	for images above: 525 pixels per inch	
	Compression: ZIP Tile Size: 128	
	Image Quality: 6-Dit	
	Grayscale images	
	Bicubic Downsampling to 🔹 350 pixels per inch	
	for images above: 525	
	Compression: ZIP Tile Size: 128	
	Image Quality. Solic	
	Monochrome images	
	Bicubic Downsampling to 🔹 1200 pixels per inch	
	for images above: 1800 pixels per inch	
	Compression: ZIP	
	Compress Text and Line Art	ames
Save Preset	Cancel Expor	ŧ

3. In the Marks and Bleeds tab, check the boxes named "Crop Marks" and "Page Information". Make sure the Offset is set to "0.125" and in Bleed and Slug, make your bleeds "0.125" in all 4 places.

		Export Adob	e PDF	
Adobe PDF Preset:	(Pres	s Quality] (modified)		
Standard:	None		Compatibility: Acrobat 8/9 (PDF 1.7)	
Central Compressions Marka and Blends Output Advanced Security Summary		Marks and Bleeds Marks - Gil Printer's Marks - Corp Narks - Bleed Marks - Color Barks - Co	Type: Default * Weight: 0.07 pt * Offnet: * * Offnet: * * Right: * *	
Save Preset			Cancel Expo	rt

4. In the Output tab, change to "No Color Conversion" and "Don't Include Profiles" The remaining tabs are set correctly. Now you can hit the Export button and save your PDF.



Congratulations! You're now ready to submit your PDF to Crown Connect for printing.

If you have any trouble or questions please be sure to call your Customer Service Representative at Crown Connect at 909.888.7531.